Integrating SimDiff 4 with git + SourceTree

Contents

Introduction	2
Configuration	2
Notes	3
Usage	4

Introduction

Git is a distributed version control system. The primary interface for working with git is the command-line, using commands such as git commit, git push, etc. However, there are a number of GUI tools that have been built on top of the command line that provide a more convenient interface for working with a repository. Some of these interfaces support interactive diff and merge tools - others do not.

The following instructions explain how to configure SimDiff 4 for use with git while using the SourceTree GUI tool.

The configuration for this repository client requires the usage of Tool Selector. ToolSelector is a utility program developed by EnSoft that can be used to select between one or more configured tools based on certain properties of the input arguments (e.g. file type). For more information about ToolSelector, please refer to the ToolSelector User Guide.pdf located at your ToolSelector directory (by default, C:\Program Files\EnSoft\SimDiff 4\utils\toolselector).

Note: if you are using a SimDiff version older than 2020a.2, then the ToolSelector directory is C:\Program Files\EnSoft\SimDiff 4\utils\toolselector-20120215-1803

Configuration

- Download sourcetree-SD4.piz from http://www.ensoftcorp.com/simdiff/repository/sourcetree-SD4.piz. Rename as sourcetree-SD4.zip and unzip it.
- 2. Copy the extracted files to your toolselector directory (by default, C:\Program Files\EnSoft\SimDiff 4\utils\toolselector).
- 3. Configure SourceTree's external diff/merge tools as follows:
 - Open SourceTree
 - Click Tools > Options
 - Enter the following information in *External Diff / Merge* section under the *Diff* tab (as shown in image below)
 - External Diff Tool: Custom
 - Diff Command: C:\Program Files\EnSoft\SimDiff 4\utils\toolselector\toolselector.exe
 - Arguments: -profile=2way \$PWD \$LOCAL \$REMOTE
 - Merge Tool: Custom
 - **Diff Command:** C:\Program Files\EnSoft\SimDiff 4\utils\toolselector\toolselector.exe
 - Arguments: -profile=3way-merge \$PWD \$MERGED \$REMOTE \$BASE \$LOCAL


Options						
		$\langle \mathbb{D}$	·N	22	8	
General Updates	5 Diff	Git	Mercurial	Custom Action	s Authentication	Network
Internal Diff View						
Diff View Font: C	onsolas, 11pt				C	hange Font
Max File Count:	20		M	ax Diff Line Coun	t: 500	
Size Limit (Text):	1024 КВ			Size Limit (Binary	: 10240 KB	
Convert tabs to		dth: 4		,		
Enable syntax h			uages			
External Diff / Merg	je					
External Diff Tool:	Custom		•			
Diff Command:	C:\Program Fil	les\EnSoft\Sin	nDiff 4\ 🛄 /	Arguments: -pro	file=2way \$PWD \$L	OCAL \$REMOT
Diff Command: Merge Tool:		les\EnSoft\Sin	nDiff 4) /	Arguments: -pro	file=2way \$PWD \$L	OCAL \$REMOT
	Custom		•		file=2way \$PWD \$L file=3way-merge \$f	
Merge Tool: Merge Command: Available command	Custom C:\Program Fil	les\EnSoft\Sin	• nDiff 4) /	Arguments: -pro		PWD \$MERGED
Merge Tool: Merge Command:	Custom C:\Program Fil	les\EnSoft\Sin	• nDiff 4) /	Arguments: -pro	file=3way-merge \$1	PWD \$MERGED
Merge Tool: Merge Command: Available command	Custom C:\Program Fil	les\EnSoft\Sin	• nDiff 4) /	Arguments: -pro	file=3way-merge \$1	PWD \$MERGED

Notes

- If SimDiff and ToolSelector are not installed to their default locations, you will need to modify the *Diff Command* and *Merge Command* paths given in step 2 above.
- If ToolSelector is installed to a location other than its default location within the SimDiff directory, you will need to update simdiff4-cd.bat with the correct absolute or relative path to simdiff4.exe.
- We strongly recommend using a 3-way diff as part of your merge process, because a 3way diff tells you not only what differs between two versions of a model, but also which changes were made in which model. 3-way diff is included in all editions of SimDiff 4.

Usage

To visualize differences between 2 versions of a model, you can click the *External Diff* menu option and SourceTree will open SimDiff to visualize the differences. The image below shows this option when comparing an unstaged file with the copy in the repository.



Similarly, SimDiff can be launched when SourceTree detects a merge conflict. This section shows the workflow to be followed when merging a branch to the checked out branch. To start, right click the branch to be merged and follow the steps described in the images below.


P File	Edit View	Repositor	y Actions	Tools H	lelp					
test_repo		×	+ -]						
$(\mathbf{+})$	€	ĵ	٢	Ŀ	٢î	80	G	0		N
Commit	Pull	Push	Fetch	Branch	Merge	Stash	Discard	Tag		Git-flow R
			All Brand	:hes 🔻 🔽	Show Remo	te Branches Da	te Order 🔻]		
🗸 🛄 FILE	STATUS		Grap	h			Descript	ion		Dat
Wor	king Copy		 P	o 🚺	master (Changes in mas	ter branch			19 Oct 201
			•	🚺 d	ev Chang	es in dev branch				10 Oct 201
🗸 🗘 BRA	NCHES		-	Adde	d first mode	4	Che	ckout		1
dev							Mei	rge	•	
O mas	ter						Reb	ase		
and the second		min		<u> </u>		-	Tag	man and		El monte en entre la



When you have a merge conflict, select the *Uncommitted Changes* branch, right-click on the conflicted file, and select *Resolve Conflicts* > *Launch External Merge Tool*.

🌳 File E	dit View	Reposito	Actions	Tools H	eip	Open		Shift+C	trl+0				_	r	- c	
test_repo		>	< 🕂 🔽			Show in E	Explorer									
()	J	ĵ	۲	ţ۶.	٢	Copy Path	h To Clipboard	d				N	Ø.	>_		(i)}
Commit	Pull	Push	Fetch All Branch	Branch	Merg Show R	External D	Diff	Ctrl+D				Git-flow	Kemote	Terminal	Explorer	Settings Jump to
✓ 🛄 FILE S			Graph			Add		Ctrl+Sh	ift+Plus				Date	*	Author	Commit
Work	ing Copy NCHES			O 👔 D de	mmitte master ev Cl d first n	Remove	type in Git LF	S Ctrl+De Shift+C				19 Oct 2 19 Oct 2	2018 9:44 2018 16:08 2018 16:04 2018 15:56	Sergio Sergio	Ferrero <sf Ferrero <sf Ferrero <sf< td=""><td>5df7fe0 ad39a30</td></sf<></sf </sf 	5df7fe0 ad39a30
O mast	5					Ignore Stop Trac Commit	-	Shift+A	lt+C					3		
> 🛆 REMO						Resolve C Custom A				·		External M Using 'Mir	lerge Tool	ß		
			Staged fil			Log Selec Annotate	ted Selected	Shift+A Shift+A	-		Resolve	Using 'The				Q 🔯 -
			A ae	ro_radmod	.mdl				Hun 7 8 9	k1 7 8 9	Restart I Mark Re Mark Ur	-			Unst	age hunk
			Unstaged	files			Stage All	Stage Selected	1 10	16	Col	nputedMod	elversion	"1.40		
			A ac	ero_radmod	.mdl				11	12 13 14 15	+ >>>>>	nputedMod	elversion	"1.41 0		
			File	Status		Log / Histo	ory	Search	12	16	Nu	mTestPoin	tedSignal	s 0		

SourceTree will show the following dialog and will open SimDiff to merge the changes.



SimDiff 4	Team								
File Edit Au	uditing View Help								
Left Model:	C:\repos\git\test_repo\aer	radmod LOCAL 7516.m	odl						
Right Model:					•••				
Base Model:	C:\repos\git\test_repo\aer	p_radmod_BASE_7516.md							
Output Model:	C:\repos\git\test_repo\aer	o_radmod.mdl							
🗢 🛃	<u>↓ 주 ↓ 주 </u>		ີ ກ ຕ √.		🔒 Legend				
		C Filters Sł	now: 📴 Whole Model 🛆	All Changes 🛕 Left Cha	anges 🛕 Right Changes				
# Output Mod	lel:		🕂 🗘 Right Model:		V				
	admod (Model)			d_REMOTE_7516 (Model)					
	nfigurationSets tive Simulink.ConfigSet		🗈 🔗 Configur	ationSets mulink.ConfigSet					
	o_radmod (Root System)		-	dmod_REMOTE_7516 (Root	t System)				
	Cartesian to Polar			esian to Polar					
	Cross-Axis Acceleration Mod	lel		s-Axis Acceleration Model	=				
	Kalman Filter Thrust-Axis Accleration Mod	el		ar Kalman Filter st-Axis Accleration Model					
	Actual Position			al Position					
	Actual Speed			al Speed					
	Actual Speed: 1> Long. V			al Speed: 1> Long. Veloci	ity:2				
	' Cartesian to Polar:1> Mu ' Cartesian to Polar:2> Mu	I		esian to Polar:1> Mux:1 esian to Polar:2> Mux:2					
	Cross Axis Position :1> C	I		s Axis Position :1> Carte	esian to Polar:1				
	Cross Axis Position :1> M	ux1:1		s Axis Position :1> Mux1	:1				
	Cross Axis Position			s Axis Position					
	Cross-Axis Acceleration Moo Cross-Axis Velocity:1> Cr	I		s-Axis Acceleration Model: s-Axis Velocity: 1> Cross					
	Cross-Axis Velocity	033 AXIST 03001111		s-Axis Velocity					
	Data is automatically loaded	at the simulation start fr	📰 Data	is automatically loaded at	the simulation star				
	Demux	1	Dem						
	' Demux:1> Cross-Axis Ac ' Demux:2> Thrust-Axis Ac			ux:1> Cross-Axis Accele ux:2> Thrust-Axis Accler					
	Display	derador Proder, 1			auonnouchi				
	III	-m-		Name a fir tiday to tiday					
O Attribute	s 🗣 Dependencies 🗿 E	ivent Log 📝 Auditing		🗐 🔎 🕞 Info about	Actual Speed				
Attribute	Output Value	Base Value	Right Value	The attributes changed in the	s of 'Actual Speed' were				
BlockT	ype Constant	Constant	Constant		ill apply this change in				
Name	Actual Speed	Actual Speed	Actual Speed	the right mode	el to the left/output				
OutDa		sfix(16)	sfix(16)	model.					
OutSc Value	al 2^0 400	2^0 400	2^0						
value	ייידן	00	▲ 500						
0:00.499	Diff: 5%	r (/ 0/13	8 0 🔇 0 🛛 🦛 0/1: 🕗 0	0 😢 0 🚫 0 🦲 ensoft				

Use SimDiff to merge the changes. Once you are done, save the model from the Simulink window and close SimDiff.

Finally, select the *Uncommitted Changes* branch, right click on the merged file, and commit it.

